
PCS WEB HOSTING EMAIL ACCOUNT INFO

INCOMING EMAIL SERVER (POP3)

POP3 Server/Host Name: mail.yourdomain.com

(Host Name is your domain name with "mail." added at the beginning)

Authentication: **Requires Name & Password ->**

(Your username or login name is your entire email address)

Standard POP3: **Port 110**

Secure STARTTLS POP3: **Port 110**

Secure SSL POP3: **Port 995**

(Port is based on choice of Authentication types — choose only one. If one does not work in your area, the other might. i.e.: If SSL setting is chosen, make sure port is set to 995, otherwise use port 110)

POP3 Email Retrieval Settings

Choice #1 **Delete From Server**

(Use #1 if NO other devices or computers are retrieving your email)

Choice #2 **Leave on Server for (a few) Days or**

Remove from Server After (a few) Days

(Choose #2 if other devices or computers are retrieving this email)

OUTGOING EMAIL SERVER (SMTP)

SMTP Server/Host Name: mail.yourdomain.com

(Host Name is your domain name with "mail." added at the beginning)

Authentication: **Requires Name & Password ->**

(Your username or login name is your entire email address)

Standard SMTP: **Port 587**

Secure STARTTLS SMTP: **Port 587**

Secure SSL SMTP: **Port 465**

(Port is based on choice of Authentication types — choose only one. If one does not work in your area, the other might. i.e.: If SSL setting is chosen, make sure port is set to 465, otherwise use port 587)

SECURE SERVER NOTE

When using a secure connection to the incoming or outgoing server, you may receive an error stating that the certificate is invalid, or otherwise insecure. Please DO accept the secure certificate anyway, permanently, and continue the process.

EMAIL ACCOUNT FEATURES

Your new email account has features you can control by logging in to special web addresses associated with your account. These are some of the things you can do without PCS Web Hosting administrator help:

- Set up an auto-reply you can enable and disable
- Fully control anti-spam filtering
- Manage email account forwarding
- Change your own password
- Access your email from a web browser (*Roundcube Webmail*)
- View all email aliases to your email account

To access your email account settings, go to: <http://mail.yourdomain.com>





To access your email via our Roundcube Webmail system, go to: <http://webmail.yourdomain.com>

PCS WEB HOSTING ADMINISTRATOR FUNCTIONS

If you need new email accounts set up, or aliases added to existing email accounts, or have any other questions, please feel free to contact Greg at PCS Web Hosting:

Website: piperhosting.net • Email: pcsweb@piperhosting.net • Message: 360-731-2805

PCS WEB HOSTING EMAIL SETTINGS (Apple iPhone/iPad)



If or when at any point you are told the server certificate is invalid or not known, please DO accept it and continue anyway. The server "verification" process may take up to 3 minutes — if it takes longer, quit Settings app and try port 587 here.

PCS WEB HOSTING EMAIL SETTINGS (Microsoft Internet Settings)

General Servers Security Advanced

Mail Account

Type the name by which you would like to refer to these servers. For example: "Work" or "Windows Live Hotmail".

Any Name You Wish Here

User Information

Name: Your Real Name

Organization:

E-mail address: user@yourdomain.com

Reply address:

Include this account when receiving mail or synchronizing

OK Cancel Apply

General Servers Security Advanced

Server Information

My incoming mail server is a POP3 server.

Incoming mail (POP3): mail.yourdomain.com

Outgoing mail (SMTP): mail.yourdomain.com

Incoming Mail Server

Email username: user@yourdomain.com

Password:

Remember password

Log on using clear text authentication

Log on using secure password authentication

Log on using authenticated POP (APOP)

Outgoing Mail Server

My server requires authentication

Settings...

OK Cancel Apply

General Servers Security Advanced

Signing certificate

Select the signing certificate below. This will determine the digital ID used when signing messages with this account.

Certificate: Select...

Encrypting preferences

Select the encryption certificate and algorithm. These are included with your digitally signed messages so others can send encrypted mail to you with these settings.

Certificate: Select...

Algorithm: 3DES

OK Cancel Apply

Logon Information

Use same settings as my incoming mail server

Log on using

Account name:

Password:

Remember password

Log on using Secure Password Authentication

OK Cancel

General Servers Security Advanced

Server Port Numbers

Outgoing mail (SMTP): 587 Use Defaults

This server requires a secure connection (SSL)

Incoming mail (POP3): 995

This server requires a secure connection (SSL)

Server Timeouts

Short Long 1 minute

Sending

Break apart messages larger than 60 KB


Delivery

Leave a copy of messages on server

Remove from server after 2 day(s)

Remove from server when deleted from 'Deleted Items'

OK Cancel Apply

 The server you are connected to is using a security certificate that could not be verified.

A certificate chain processed, but terminated in a root certificate which is not trusted by the trust provider.

Do you want to continue using this server?

Yes No

If or when at any point you are told the server certificate is invalid or not known, please DO accept it and continue anyway. The "validation" process may take up to 3 minutes.

PCS WEB HOSTING EMAIL SETTINGS (Mozilla Thunderbird Settings)

Your Account

- Server Settings
- Copies & Folders
- Composition & Addressing
- Junk Settings
- Disk Space
- Return Receipts
- Security
- Outgoing Server (SMTP)

Account Name:

Default Identity

Each account has an identity, which is the information that other people see when they read your messages.

Your Name:

Email Address:

Reply-to Address:

Organization:

Signature text: Use HTML (e.g., bold)

Attach the signature from a file instead (text, HTML, or image):

Attach my vCard to messages

Outgoing Server (SMTP):

Your Account

- Server Settings
- Copies & Folders
- Composition & Addressing
- Junk Settings
- Disk Space
- Return Receipts
- Security
- Outgoing Server (SMTP)

Server Type: POP Mail Server

Server Name: Port: Default: 110

User Name:

Security Settings

Connection security:

Authentication method:

Server Settings

Check for new messages at startup

Check for new messages every minutes

Automatically download new messages

Fetch headers only

Leave messages on server

For at most days

Until I delete them

Message Storage

Empty Trash on Exit

Message Store Type:

Local directory:

Your Account

- Server Settings
- Copies & Folders
- Composition & Addressing
- Junk Settings
- Disk Space
- Return Receipts
- Security
- Outgoing Server (SMTP)

When managing your identities you can use a server from this list by selecting it as the Outgoing Server (SMTP), or you can use the default server from this list by selecting "Use Default Server".

youremail@yourdomain.com - mail.yourdomain.com	<input type="button" value="Add"/>
	<input type="button" value="Edit..."/>
	<input type="button" value="Remove"/>
	<input type="button" value="Set Default"/>

Description: <not specified>

Server Name: mail.yourdomain.com

Port: 587

User Name: youremail@yourdomain.com

Authentication method: Encrypted password

Connection Security: STARTTLS

Settings

Description:

Server Name:

Port: Default: 587

Security and Authentication

Connection security:

Authentication method:

User Name:

If or when at any point you are told the server certificate is invalid or not known, please DO accept it and continue anyway. Certificate warning will be presented when sending the first email, and when receiving the first email.